

## Technical Recommendation

### Using Gramoxone SL 2.0 as a Tillage Aid in



#### Tillage Aid Use Directions:

- Gramoxone SL 2.0 at 3 pt/acre + NIS @ 1 qt/100 gal
  - Corn: add atrazine at 0.5–1.0 qt/acre
  - Soybean: add metribuzin at 2 oz per acre (2 oz of a 75 DF product)
- Apply a minimum of 15 gpa, 20 gpa preferred, using a medium spray droplet
- Add NIS to carrier before adding any other tank-mix components
- UAN makes an excellent carrier and may improve performance due to volume and increased burn
- When using liquid fertilizers such as 28% N, NIS should still be used
- Use full rate residual tank-mixes or overlapping residuals to maximize control and eliminate excess in crop applications of straight glyphosate. See label for specific labeled tank-mix partners

#### Use Restrictions:

- Avoid muddy water or suspension-type fertilizers as carriers
- Use of proper PPE is required according to label
- Do not use AI type nozzle tips, and avoid flood tips
- Do not apply 2,4-D if planting soybeans within 7 days of planting or crop injury may occur
- Do not apply Gramoxone SL 2.0 to emerged crops or crop injury will occur

TMK 4.16.2015